Archived:Get Manufacturer and Model number of the device using CTelephony

Archived: This article is archived because it is not considered relevant for third-party developers creating commercial solutions today. If you think this article is still relevant, let us know by adding the template {{ReviewForRemovalFromArchive|user=~~~~|*write your reason here*}}.

Reviewer Approved

Overview

CTelephonyReader implementation illustrates how to get Manufacturer and Model number of the device in S60 3rd Edition with CTelephony API.

The implementation is pretty simple, and when using this one only thing to do in calling class is to implement the callback interface and then to construct an instance of the CTelephonyReader.

Headers Required

```
#include <Etel3rdParty.h>
```

Library Needed

```
LIBRARY etel3rdparty.lib
```

Capability Required

```
Capability None
```

TelephonyReader.h

```
#ifndef __TELEPHONYREADER_h__
#define __TELEPHONYREADER_h__

#include <Etel3rdParty.h>
class MTelephonyObserver
{
public:
 virtual void GetPhoneId(const TDesC& aManufacturer,const TDesC& aModel) = 0;

};

class CTelephonyReader : public CActive
 {
public:
 static CTelephonyReader* NewL(MTelephonyObserver* aObserver);
 static CTelephonyReader* NewLC(MTelephonyObserver* aObserver);
 void ConstructL(void);
 ~CTelephonyReader();
protected:
 void DoCancel();
 void RunL();

private:
 CTelephonyReader(MTelephonyObserver* aObserver);

private:
 MTelephonyObserver*    iObserver;
 CTelephony*      iTelephony;
 CTelephony::TPhoneIdV1   iPhoneIdV1;
 CTelephony::TPhoneIdV1Pckg  iPhoneIdV1Pckg;
};

#endif //__TELEPHONYREADER_h__
```

TelephonyReader.cpp

```
#include "TelephonyReader.h"

CTelephonyReader* CTelephonyReader::NewL(MTelephonyObserver* aObserver)
    {
    CTelephonyReader* self = NewLC(aObserver);
```

 (C) Copyright Nokia 2013. All rights reserved.

```
    CleanupStack::Pop(self);
    return self;
    }


CTelephonyReader* CTelephonyReader::NewLC(MTelephonyObserver* aObserver)
    {
    CTelephonyReader* self = new (ELeave) CTelephonyReader(aObserver);
    CleanupStack::PushL(self);
    self->ConstructL();
    return self;
    }


CTelephonyReader::CTelephonyReader(MTelephonyObserver* aObserver)
:CActive(0),iObserver(aObserver),iPhoneIdV1Pckg(iPhoneIdV1)
{
}

CTelephonyReader::~CTelephonyReader()
{
 Cancel();
 delete iTelephony;
}

void CTelephonyReader::ConstructL(void)
{
 CActiveScheduler::Add(this);

 iTelephony = CTelephony::NewL();

 iTelephony->GetPhoneId(iStatus,iPhoneIdV1Pckg);

 SetActive();
}

void CTelephonyReader::DoCancel()
{
 iTelephony->CancelAsync(CTelephony::EGetPhoneIdCancel);
}


void CTelephonyReader::RunL()
{
 if(iStatus == KErrNone)
 {
  iObserver->GetPhoneId(iPhoneIdV1.iManufacturer,iPhoneIdV1.iModel);
 }
}
```

Example Code

- Example code

Related Link

- Archived:Get MCC MNC using CTelephony
- Archived:Get Operator Name using CTelephony

http://developer.nokia.com/Community/Wiki/Archived:Get_Manufacturer_and_Model_number_of_the_device_using_CTelephony (C) Copyright Nokia 2013. All rights reserved.

http://developer.nokia.com/Community/Wiki/Archived:Get_Manufacturer_and_Model_number_of_the_device_using_CTelephony (C) Copyright Nokia 2013. All rights reserved.